




# VisionPro 6.1 Quick Reference



# VISION PRO Vision Software

# **VisionPro PC Requirements**

Your PC hardware and software must meet the requirements listed in this section.

### **Minimum PC Requirements**

- IBM or compatible Pentium PC with MMX/SSE2 instruction set
- (Optional) One open PCI slot for a Cognex frame grabber or direct connect camera adapter such as Firewire or GigE.
- (Optional) One open PCI Express slot for an MVS-8600e frame grabber, MVS-8500e frame grabber, Gigabit Ethernet adapter, or FireWire adapter
- 512 MB RAM for Windows XP; 1 GB for Windows Vista and Windows 7
- 400 MB free disk space prior to installation
- 1024 x 768 display with a display setting of 96 DPI
- PCI, PCI Express (recommended), or AGP video adapter
- Internet Explorer 6 SP1
- Microsoft Visual Studio 2005/2008, or Microsoft Visual Studio 2005/2008 Express with SP1, for VB.NET, C# or managed C++ (for development of .NET applications only, not required for deployment)
- Microsoft .NET 2.0 SP1 Framework

The VisionPro installation utility will install the Microsoft .NET 2.0 Framework if your development or deployment PC does not have it already installed.

### **Operating Systems**

Support for development and deployment on single or multiprocessor machines using the following native languages: English, Japanese, German, Korean, and Simplied Chinese.

- XP Home and Professional: 32-bit SP3
- Vista 32-bit and 64-bit SP3
- Windows 7 32-bit and 64-bit

# **Installing VisionPro**

**Note**: The 64-bit version of VisionPro uses a separate installer that is not included on the VisionPro DVD, but can be downloaded from http://www.cognex.com/Support/VisionPro/

1. Uninstall any existing VisionPro software.

Use the **Add or Remove Programs** feature of the Windows Control Panel to remove any of the following programs if they are present:

Cognex VisionPro

**Cognex Drivers** 

**Cognex Japanese Documentation** 

**Cognex Software Licensing Center** 

Restart your PC if prompted.

2. Turn off the PC and install the vision hardware necessary for your vision application.

For Cognex hardware, follow the installation instructions found in the hardware manuals supplied in the \Doc directory of your VisionPro DVD. For non-Cognex hardware, follow the manufacturer's installation instructions.

3. Attach the necessary cameras, I/O devices and security key and turn on the PC.


If you installed a Cognex frame grabber or an adapter for IEEE 1394 (FireWire) or Gigabit Ethernet, Microsoft might display the Found New Hardware Wizard. Select Cancel.

4. Install the VisionPro software.

Exit all applications and insert the VisionPro DVD. The installation utility should start automatically. If it does not, double-click on the file setup.exe located on the DVD.

- You must have Administrator privileges to install VisionPro.
- If your PC does not already have Microsoft Visual Studio C++ 2005 Redistributable installed, it will automatically be installed.
- If your PC requires an update to the Windows Installer, it will automatically be updated. Depending on how your system is configured, you might see a message about this update taking place.
- If you installed a Measurement Computing Digital

I/O PCI or USB bus adapter, you must use the **Optional Features** of the **Custom Setup** to select the Measurement Computing Driver, as shown:



- 5. (Optional) Install the Japanese version of the documentation.
  - You have the option of installing Japanese versions of the VisionPro documentation.
- 6. (Optional) By default the installer includes the Cognex Software Licensing Center utility, which allows you to use a software license file instead of using a Cognex frame grabber or a Cognex-supplied security dongle to provide license information.
- 7. Install the VisionPro Hardware Drivers

By default the **Cognex Drivers** utility will install all the frame grabber drivers, the Cognex FireWire DCAM driver, the GigE Vision drivers, and the driver for all supported security keys. You can, as an option, select **Custom** in the **Setup Type** dialog and pick the specific drivers you want installed. The drivers are Authenticode signed with a Cognex certificate.

You must install at least one driver to use the VisionPro software, unless you are using software security to provide license information.

If you do not install any drivers during the initial software installation and want to install one or more drivers later, insert the VisionPro installation DVD and double-click on setup.exe in the \drivers directory to launch the Cognex Drivers utility.

Microsoft Windows XP SP3 does not support the maximum speed on IEEE 1394b FireWire adapters. Downgrading the Windows XP FireWire bus driver to the SP1 version is required for FireWire cameras to work correctly on an IEEE 1394b adapter. The Cognex Drivers installer will automatically launch the utility XPDCAMFix.exe if this downgrade is required. The utility will prompt you to click on **Downgrade**. The downgrade utility modifies only files needed for proper IEEE 1394b operation, and does not affect any other Microsoft XP SP3 bus drivers. See the FireWire Cameras User's Guide, available from the Start->Cognex->VisionPro->Documentation->English->Hardware Manuals->FireWire Cameras User's Guide.

Reboot the PC if prompted. If you install additional image acquisition hardware later, use the Windows Control Panel to select the Cognex Drivers software for repair and modifications.

# **Configure the Gigabit Ethernet Network** Adapter

If you installed a Gigabit Ethernet network adapter, you must use the Cognex GigE Vision Configuration utility to assign an IP address to the adapter and any cameras connected to it. Each network adapter (and each port of a multi-port adapter) must have its own IP address on its own subnet. Each camera must have its own IP address on the same subnet as its network adapter, otherwise the camera and the adapter will not be able to communicate.

See the GigE Vision Cameras User's Guide, available from the **Start** menu, for more information about configuring your PC to use GigE Vision cameras.

# **Working with Third-Party Imaging Devices**


Manufacturers of cameras, frame grabbers, and other devices that generate digital images can make these images available to the VisionPro Imaging Device interface. Refer to the manufacturer's web site for specific support information.

# **Configure the Measurement Computing** PCI bus adapter

If you installed a Measurement Computing Digital I/O PCI bus adapter, the **Found New Hardware** wizard will appear. Use the wizard to install the driver automatically from the VisionPro software already installed.

Do not install the Measurement Computing software development kit (SDK). This VisionPro release contains the programming interface necessary to communicate with the Measurement Computing discrete I/O hardware.

In addition, double-click on the **InstalCAL** application installed on the Windows desktop to complete the installation, ensuring the board is configured as Board# 0, as shown:



Right-click on the board number and select **Change Board#** if necessary.

# **Acquire a Software License**

If you are not using a Cognex frame grabber or a Cognex-supplied security dongle to provide license information to VisionPro, then you must acquire and install a software license file.

Cognex offers the option of software licensing through the use of an Activation ID, which you use to connect to the Cognex license server and enable licensed VisionPro features for any given PC.

Contact your Cognex sales representative or visit the web site www.cognex.com/support/VisionPro for more information. The topic **Understanding VisionPro Security**, available in the online VisionPro Documentation, provides detailed information on how VisionPro implements software security.

### VisionPro Overview

VisionPro provides an interactive development environment that you can use to assemble tools, configure acquisition and I/O, and deploy robust, high-performance applications with full-featured operator interfaces. VisionPro also provides a full-featured toolkit that you can program in .NET using C#, VB.NET or managed C++.

### **VisionPro Development Overview**

VisionPro consists of a set of development tools:

- QuickBuild is an interactive application builder that lets you define an application comprising multiple Jobs. For each job, you define and configure the image source (a Cognex frame grabber, FireWire camera, GigE Vision camera, imaging device for a 3rd party acquisition adapter, or an image file), then add the vision tools and the results analysis logic. You can run the Jobs interactively, using either manual, triggered, or automatic operation.
- Within OuickBuild, the **Communications Explorer** provides an interface to Cognex I/O hardware. You can link specific data items and results from an application to output lines or a TCP/ IP connection to network hardware. You can configure systemlevel output such as a job-ready signal or a system heartbeat, and input signals to control when your vision application executes.
- Using the **Application Wizard** you can generate a complete operator interface that encapsulates the application you created using QuickBuild and the Communications Explorer. The Wizard-generated application includes an executable Windows program, fully commented source code, as well as the job and I/O configuration data. Depending on the options you specify, the application can also provide full configuration control over the job internals at run time.

The following figure provides an overview of a basic VisionPro development process:



### **Advanced Development Capabilities**

In addition to using the Application Wizard to package your VisionPro application for deployment, you can also write a custom application around the configured Jobs, or you can create your entire application using C#, managed C++ or VB.NET directly with the underlying VisionPro components. The following are the three most common advanced development paths towards a customized, deployable application:


- Interactive development with OuickBuild plus a customized Application Wizard-Generated Operator Interface
  - Because the Application Wizard generates a VB.NET or C# application, including source code, you can use Microsoft Visual Studio to view and modify the generated operator interface. This makes it easy to customize the look and feel of the application by adding controls and display values from other system components.
- Interactive Development plus a Custom-Written Operator Interface
  - VisionPro's .NET programming interface includes functions to load and operate a saved QuickBuild application (in fact, the Wizard-generated application uses these functions). Instead of using the Wizard-generated code, you can simply write your own Visual Studio application to load and control the saved OuickBuild application.
- Custom application using the VisionPro programming interface The .NET programming interface lets you create entire applications using C#, managed C++ or VB.NET, providing low-level control of image acquisition, and analysis.

The VisionPro online documentation provides an example of creating a deployable VB.NET application by loading a QuickBuild application and adding a custom graphical user interface.

# **Getting Started With VisionPro**


### **Develop your Application with QuickBuild**

OuickBuild is a rich interactive development environment that lets you create and manage multiple Jobs, each of which contains multiple tools and has the ability to run automatically whenever an image is available:



### **Configure the Communications Explorer**

Once your job is working properly, use the Communications Explorer to configure the signals carried by your discrete I/O hardware and establish any TCP/IP links you need to exchange data with other network hardware:



### Use the Application Wizard to Build a Deployable **System**

After saving your complete QuickBuild application, including all Jobs and communications information, launch the VisionPro Application Wizard and create a deployable operator interface:



# **Sample Jobs and Programs**


VisionPro installs a large set of Visual Studio programming samples for a variety of tools. Each sample solves a specific vision task, and were created using C# or VB.NET.

The installation utility installs a set of programming samples, which are located by default in \Program Files\VisionPro\Samples\ Programming.


Likewise, QuickBuild includes a set of sample Jobs that demonstrate a variety of vision tasks, and can be accessed through the Navigation pane as shown in the figure on the following page.

# **QuickBuild Reference**


### **QuickBuild Window**



### Job Editor




### **Tool Edit Control**




### **Communications Explorer**



### **Application Wizard**



### **Generated Operator Interface**



### For More Information

## In QuickBuild

Click the question mark in any window to display a pop-up menu of options for displaying information related to the current vision tool or QuickBuild component.

### From Microsoft Windows

From the **Start** menu, select

Cognex-VisionPro->Documentation for a list of available titles.





2 rue René Laennec 51500 Taissy France Fax: 03 26 85 19 08. Tel: 03 26 82 49 29 Fax: 03 26 85 19 08, Tel: 03 26 82 49 29

Email:hvssystem@hvssystem.com Site web: www.hvssystem.com

### Copyright © 2010 Cognex Corporation All Rights Reserved

This document may not be copied in whole or in part, nor transferred to any other media or language, without the written permission of Cognex Corporation.

Portions of the hardware and software provided by Cognex may be covered by one or more of the U.S. and foreign patents listed below as well as pending U.S. and foreign patents issued after the date of this document are listed on the Cognex web site at http://www.cognex.com/ patents.

```
5481712, 5495537, 5548326, 5583954, 5602937, 5640200, 5751853,
5768443, 5825913, 5850466, 5872870, 5901241, 5943441, 5978080,
5978521, 5987172, 6005978, 6039254, 6064388, 6075881, 6137893,
6141033, 6167150, 6215915, 6240208, 6324299, 6381366, 6381375,
6411734, 6421458, 6459820, 6490375, 6516092, 6563324, 6658145,
6687402, 6690842, 6697535, 6718074, 6748110, 6771808, 6804416,
6836567, 6850646, 6856698, 6920241, 6959112, 6963338, 6973207,
6975764, 6985625, 6993177, 6993192, 7006712, 7016539, 7043081,
7058225, 7065262, 7088862, 7164796, 7190834, 7242801, 7251366,
7313761, EP0713593, JP3522280, JP3927239
```

VisionPro, the VisionPro logo, Cognex and the Cognex logo are trademarks, or registered trademarks, of Cognex Corporation. Microsoft, Windows, and the Windows logo are trademarks, or registered trademarks of Microsoft Corporation in the United States and/or other countries.